Instructions for using WindNinja's command line interface (cli)



5/31/2013

Introduction

To allow WindNinja to be used more easily by other programs or through scripting, a command line interface (cli) has been developed. Programmers should find this very useful, however, most WindNinja users (fire managers and fire modelers) will not use the cli. This short paper gives a description of how to use the cli. It assumes that you have some experience running programs from the command line (terminal).

The WindNinja cli is provided as a separate executable called "WindNinja_cli.exe". This executable comes with the normal installation of WindNinja for the Windows operating system (in the "bin" directory). It is also possible to run WindNinja from a Linux operating system. Users interested in the Linux version should contact Jason Forthofer at jaforthofer@fs.fed.us. The cli executable is dependent on all of the dynamic link libraries provided in the "bin" directory (libcurl.dll, gdal18.dll, etc.) except the Qt libraries "Qt4Core4.dll" and "QtGui4.dll" (used only in the gui version).

Setting the environment

To do a run from the terminal, it is recommended that you add the WindNinja bin directory to the "Path" environment variable. This can be done on some Windows systems by doing this:

- 1. Right-click My Computer and select Properties.
- 2. Select the Environment page.
- 3. In the System Variables area, highlight the current "Path" and click Edit.
- 4. Add the new path *to the end* in the format VALUE1;VALUE2;. *Be sure you don't delete any of the other paths!!* For example, if WindNinja 2.1.0 was installed in the default directory, add this to the end of the current path: ; c:\WindNinja\WindNinja-2.1.0\bin
- 5. Click **OK** to close all of the windows you have opened.
- 6. The changes take effect immediately, however if you had a terminal open before you made these changes, you should close it and reopen one for the new settings to take effect.

Starting a run

A cli run must be started from a terminal (or "spawned" or something equivalent when called from another program). You type the name of the cli executable ("WindNinja_cli.exe") and then options (arguments) to specify information about the run. The options can either be specified directly from the terminal, or by using a configuration file or response file, or some combination of these. To use the terminal, just type the executable followed by the options and associated values. To use a configuration file, just type the name of the executable followed by the name of the configuration file (absolute or relative path from the location of the executable file). To use a response file, type the name of the executable followed by "@name" where "name" is the name of the response file. All of these methods of starting a run with the cli are described in more detail below.

Available options

The available options with descriptions can be viewed by typing: WindNinja_cli.exe --help (note that it is antional to add the file avtension " ave" to "WindNin

(note that it is optional to add the file extension ".exe" to "WindNinja_cli") A list of the available options should be shown and look similar to this:

```
jforthofer@lucky14: ~/windninja/trunk
File Edit View Search Terminal Help
forthofer@lucky14:~/windninja/trunk$ WindNinja --help
Allowed options:
Generic options:
 --version
                       print version
 --help
                       produce help message
                       configuration file ('config file' flag not required)
 --config_file arg
 --response file arg
                       response file (can be specified with '@name', also)
Simulation options:
 --num threads arg (=1)
                                       number of threads to use during
                                        simulation
 --elevation file arg
                                        input elevation path/filename (*.asc,
                                        *.lcp, *.tif, *.img)
 --initialization method arg
                                        initialization method
                                        (domainAverageInitialization,
                                        pointInitialization,
                                        wxModelInitialization)
 --time zone arg
                                        time zone (common choices are:
                                        America/New York, America/Chicago,
                                       America/Denver, America/Phoenix,
                                        America/Los Angeles, America/Anchorage;
                                       all choices are listed in
                                       date time zonespec.csv)
                                        type of wx model to download
 --wx model type arg
                                        (NCEP-NAM-12km-SURFACE,
                                       NCEP-NAM-Alaska-11km-SURFACE.
                                        NCEP-NDFD-5km, NCEP-RUC-13km-SURFACE)
 --forecast duration arg
                                        forecast duration to download (in
                                        hours)
```

(continued...)

Options can be used in any order. Each option has an associated value that can be a string, integer, or float value depending on the option. Some of the options have a default value that is used if the option is not specified. The default value is shown in parenthesis (for example, the --num_threads option shown above is defaulted to 1 thread).

Depending on the type of run you are trying to do, certain options are required and some are mutually exclusive (ie. can't both be specified at the same time). If you specify two mutually exclusive options, or don't specify a required option, a message with information on what you did wrong should be shown. There are too many possible combinations of options to describe here. Instead, some example configuration files have been included with the installation to show which options to specify for common types of runs. We recommend starting with one of these example configuration files and modifying them for your purpose.

Starting a run using the terminal

The terminal can be used to start a run by simply typing "WindNinja_cli" followed by the option/value pairs separated by a space or "=" like this:

WindNinja_cli --num_threads 4 --vegetation=trees ...etc...

Starting a run using a configuration file

The configuration files are just text files that list the options and associated values. The example configuration files provided with the normal WindNinja installation are located in the installation's "etc/windninja/example-files" directory. The files are:

cli_domainAverage.cfg

cli_domainAverage_diurnal.cfg

cli_pointInitialization_diurnal.cfg

cli_wxModelInitialization_diurnal.cfg

cli_wxModelInitialization_downloadDEM_diurnal.cfg

The filenames give insight into what sort of WindNinja run the configuration file does. For example, the "cli_wxModelInitialization_diurnal.cfg" file does a weather forecast model initialized simulation with diurnal flow turned on. You can open each file to see additional comments describing what the run is doing. The format of a configuration file is as follows:

- "#" denotes a comment (to the end of the line)
- Setting an option is like this: *option_name = option_value* Note that the "--" is not used in the option name in a configuration file (but it is used if specified in the terminal or response file).

The contents of a configuration file are shown below:

```
#
  This is an example command line interface (cli) configuration file.
#
#
# This particular file illustrates the necessary options settings to
# do a weather forecast model initialization run with diurnal winds.
# The weather model is downloaded via the Internet. The mesh is set
  to a specified resolution of 250 meters.
#
#
num_threads
                                          1
elevation_file
                                          C:/XXXX/mackay_gtf_dem.tif
                                    =
initialization_method
                                          wxModelInitialization
                                    =
time_zone
                                          America/Denver
                                    =
wx_model_type
                                    =
                                          NCEP-NAM-12km-SURFACE
forecast_duration
                                    =
                                          100
output wind height
                                          20.0
                                    =
units_output_wind_height
                                          ft
                                    =
vegetation
                                    =
                                          trees
diurnal_winds
                                    =
                                          true
mesh resolution
                                    =
                                          250.0
```

WindNinja Command Line Interface Instructions

units_mesh_resolution	=	m
write_goog_output	=	true
write_shapefile_output	=	true
write_ascii_output	=	true
write_farsite_atm	=	true
write_wx_model_goog_output	=	true
write_wx_model_shapefile_output	=	true
write_wx_model_ascii_output	=	true

To run this particular configuration file, you would just type:

```
WindNinja_cli C:/XXXX/cli_wxModelInitialization_diurnal.cfg
```

where "XXXX" represents the rest of the path to the file.

Starting a run by specifying options from both the terminal and a configuration file

A very useful feature of the WindNinja cli is that you can specify options from both the terminal and a configuration file at the same time. One way to use this feature would be to put the more "general" options in a configuration file, but then specify other more specific options for the run via the terminal. If the same option is specified in both the terminal and the configuration file, the terminal value is used.

As an example of this, you could use the configuration file shown above but "override" the elevation file, vegetation, and number of threads options by typing this:

WindNinja_cli C:/XXXX/cli_wxModelInitialization_diurnal.cfg
--elevation_file C:/XXXX/canyon_fire.asc --vegetation grass
--num_threads 4

Response files

Some operating systems apparently have very low limits of the command line length. One common way to work around those limitations is using *response files* (instead of configuration files). A response file is just a configuration file which uses the same syntax as the command line (rather than the configuration file syntax described above). If the command line specifies a name of response file to use, it's loaded and parsed in addition to the command line. *We recommend using a configuration file rather than a response file simply because the syntax is more readable and comments are allowed. The response file method is provided for rare situations where using it might be necessary.*

An example response file is located in the installation's "example-files" directory called:

cli_domainAverage_diurnal.rsp

To run this response file, you would just type:

```
WindNinja_cli @C:/XXXX/cli_wxModelInitialization_diurnal.rsp
```

where "XXXX" represents the path to the file. Notice the "@" character preceding the response file name, which identifies it as a response file.